

Testing

- May better indicate how animal management and other factors actually affect nutrient content.
- Good sampling technique is critical for having confidence in test results.
- Critical for estimating nutrient loading



TECHNIQUE

- Sample from loaded spreaders is best
- Variability
 - Greater from barnyard and pack vs. loaded spreader
- Take several samples helps reduce variability.
- Variability exists even under the most ideal conditions

5-gallon bag

- Thoroughly mixed
- 24 subsamples
 - Still high variability
 - Less with liquid
 - More with solids

TIME - Dairy Manure

- Over 3-yr period
 - Little change in N
 - Larger change in K
- Consistent Results Possible
 - With good representative sampling
 - Same herd management




TIME - Chicken Manure

- Over 5-month period
 - High variability for all parameters
- Inconsistent results due to
 - Seasonal changes in feed
 - 5 to 6 batches of birds before sampling

Use Long-term Farm Averages

- Only if herd and manure management practices have not changed.
- IF no baseline
 - Develop a historic record over 2 3 years
 - Sample just prior to land application
 - Note time of year to monitor potential seasonal variability.

Lagoon water N variation over time






SAMPLING RECOMMENDATIONS



Manure samples from private & public labs



However

- Most livestock operations still don't sample manure. Why?
 - Sample Heterogeneity
 - Inherent difficulty in obtaining a representative sample



General Guideline

- Avoid Heterogeneity by not sampling:
 - Bedded packs
 - Unagitated liquid storage facilities
- Poorly sampled systems will not improve accuracy of estimating N and P loading
- Adequate subsampling very important

RECOMMENDED PROCEDURES

- Mixing a solid sample
 - Pile manure
 - Shovel from outside to inside until well mixed
- Fill a 1-gallon heavy-duty sealable plastic bag half full with composite sample
- Squeeze air out, close, and seal
- Store below freezing unless delivered immediately.

Sample While Loading

- Take at least 5 samples while loading several spreader loads
- Combine to form one composite sample
- Thoroughly mix the composite sample and remove a 1-lb subsample using a one-gallon plastic bag.
- Do not sample directly from pack or bed

Sample While Spreading

- Take at least 5 samples while loading several spreader loads
- Combine to form one composite sample
- Thoroughly mix the composite sample and remove a 1-lb subsample using a one-gallon plastic bag.
- Do not sample directly from pack or bed

Sample Stockpiled Manure

Take 10 sub-samples from different locations around the pile at least 18-inches below the surface.
Mix in a 5-gallon pail
Place a 1-lb composite sample in a gallon plastic bag.

Number of Sub-samples 10% error - Colorado study


Type	TKN	P	K	NH ₄	NO ₃		
Beef	17	20	32	121	692		
Dairy compost		5	119	92	191		
Dairy manure		49			1914		
Curkey			13				
Inorg. N not recommen							

Number of Subsamples for TKN

Type	CI (95%)	Std Dev	Subsamples
Pen	1.5 – 2.6	0.22	7
Separator	0.3 - 3.0	0.72	-
Stockpiled	1.0 – 1.9	0.35	30
Composted	0.1 - 2.0	0.06	2


From NM 1999 survey

Pounds per dry ton




- ☐ Ash
- Carbon
- Sodium
- Org. N
- Inorg. N

- S
- Ca Ca
- □ Mg
- Zn
- Fe
- □ Mn
- Cu
- □ CI



Mineralization



Org-N

Time

Microbes

Moisture

Warm Temperature

NH₄-N

Soil

Microbes

NO₃-N



- In the following procedures thoroughly mix
- A plunger works well for mixing liquids in a 5-gallon pail.
- Fill a 1 qt plastic bottle not more than ¾
 full with the composite sample
- Store in freezer if not delivered to lab immediately.

LIQUIDS – from storage

- Agitate before sampling.
- Collect at least 5 samples in a 5-gallon pail
- Stratification
 - N and K more concentrated in the top liquid
 - P more concentrated in bottom solids





- Place buckets around field
- Collect at least 5 samples
- Transfer on composite sub-sample to a one-quart bottle after mixing with a plunger

Selected Slurry Characteristics

	Org-N (mg/L)	NH ₄ -N (mg/L)	Nitrate-N (mg/L)	Cl (mg/L)	TDS mg/L
Median	142	203	0.10	353	290
Ave	165	246	0.14	486	3 3 49
Max	760	998	0.8	2086	1210
Min	1	32	0.1	106	$\frac{1}{279}$
Std. Dev.	140	154	0.1	373	215
					6

November 2003 NM





Water Quality


- Electrical Conductivity
 - 4.8 mmhos/cm
- pH
 - **7.8**
- Solids
 - 0.4 % by volume
- Total Dissolved Solids
 - 2903 ppm
- Chloride
 - 353 ppm

- Irrigation purposes
 - < 3 mmhos/cm
- pH
 - **< 8**

- TDS
 - **<2000**
- Chloride
 - <69 ppm


Lagoon Water N - Nov 2003









Relative Basis



Lagoon Water N




Lagoon Water P & K



SAMPLE IDENTIFICATION

- Farm
- Date
- Method of Application
- What tests
- Keep frozen until shipped or delivered to lab.
- Ship early in the week (Mon Wed) & avoid holidays and weekends.



Test Minimums

- Total Kjeldahl N
 - Organic-N +Ammonium-N
- Nitrate-N
- Chloride

- Phosphate-P or Total P
- Potassium-K or Total K
- Total salt
- Sodium

 Liquids may require preservation by pH reduction